


Setting up an Android phone for SMTP

1. Tap on Applications



2. Tap on Email



3. Enter your email address and password (tick "Set as premium account" if this is your main email account), and then tap on Manual setup

The screenshot shows the 'Set up email' screen. At the top, it says 'Set up email' and 'You can configure email for most accounts in a few steps'. Below this are two text input fields: 'Email address' containing 'example@domain.co.za' and 'Password' containing a masked password '.....'. Below the password field are two checkboxes: 'Set as premium account (POP/IMAP)' which is checked, and 'Show password' which is also checked. At the bottom are two buttons: 'Manual setup' and 'Next' with a green arrow icon. Blue arrows with numbers point to specific elements: arrow 3 points to the 'Email address' field, arrow 4 points to the 'Password' field, arrow 5 points to the 'Set as premium account' checkbox, and arrow 6 points to the 'Manual setup' button.

4. Enter your username, password, IMAP server and port number, then tap Next

The screenshot shows the 'Incoming server settings' screen. It contains several input fields: 'User name' with 'example@domain.co.za', 'Password' with a masked password '.....', 'IMAP server' with 'imap.domain.co.za', 'Security type' with a dropdown menu set to 'None', 'Port' with '143', and 'IMAP path prefix' with 'Optional'. At the bottom is a 'Next' button. Blue arrows with numbers point to specific elements: arrow 8 points to the 'User name' field, arrow 9 points to the 'Password' field, arrow 10 points to the 'IMAP server' field, arrow 11 points to the 'Security type' dropdown, arrow 12 points to the 'Port' field, and an unlabeled arrow points to the 'Next' button.

5. Enter your username, password, POP3 server and port number, then tap Next

The screenshot shows the 'Incoming server settings' screen. It has a title bar with a back arrow, signal strength, battery, and time (08:20). The settings are as follows:

- User name:** example@domain.co.za (arrow 14)
- Password:** masked with dots (arrow 15)
- POP3 server:** pop3.domain.co.za (arrow 16)
- Security type:** None (arrow 17)
- Port:** 110 (arrow 18)
- Delete email from server:** Never
- Next button:** at the bottom.

6. Enter your SMTP server as in the below image; security type is None and port number is 25. "Require sign-in" must be ticked, and the username and password must be entered as supplied to you. Please note you can also set the Security type to SSL (Accept all certificates) and then change the port number to 587, 465 or 443. Then tap Next

The screenshot shows the 'Outgoing server settings' screen. It has a title bar with a back arrow, signal strength, battery, and time (11:01). The settings are as follows:

- SMTP server:** smtp.adept.co.za (arrow 19)
- Security type:** None (arrow 20)
- Port:** 25 (arrow 21)
- Require sign-in:** checked (arrow 22)
- User name:** example@domain.co.za (arrow 23)
- Password:** masked with dots (arrow 24)
- Next button:** at the bottom.

7. Select how often your phone should check for new emails, and whether you should be notified of new emails, then tap Next



8. Fill in the account name and Your name fields, then tap on Done

